


Align to a DWG Survey

In Revit




Shared Coordinates Separate Video!



Fundamentals Origins and coordinates Units in DWG/Revit Survey preparation Positioning methods D Command (AutoCAD)



Origins and Coordinates



Survey Point - Internal
Shared Site:
N/S 0.0
E/W 0.0
Elev 0.0

Origin of project coordinates system

Should be kept somewhere relative to the project scope

A known, surveyed point


Should be the surveyed marker *or* the origin of the coordinates system (0,0,0 relative to MGA etc.)



Why can't I see them?!



Revit Origin / Startup Location




Never technically moves
Everything else moves around it



Browsers Properties

Revit Origin / Startup Location Mark/track it!!!





Revit Origin / Startup Location

Important! It is Dynamo's origin




Project Units in Revit/AutoCAD (UN)

Drawn/Modelled Units in Revit/AutoCAD (UN)



Survey Preparation



Look at the file before you Link it!



aussie BIM guru


Survey Features




- 1. North marker
- 2. N/E survey points
- 3. Contours
- 4. Property boundary
- 5. Clean file of text?
- 6. Units?




Example: Simple Survey



Link Positioning





- 1. NB Auto-Detect does not always work
- 2. Usually best ticked off
- 3. If no aligned, use Manual Center





Extents Issue







DWG files of greater extents than this will also revert to **Centre to Centre** without telling you! Even if you choose **Origin to Origin**



Some Solutions




OR







Survey Alignment Process




Part 1: Place/Align Survey














Part 2: Rotate True North








Part 3: Specify Coordinates






Part 4: Triangulate (Check)






Part 5: Levels/Contours





Relativity Demonstrated



NB this is not a Shared Coordinates set-up! Upcoming Video







